

## dvtm - Dynamic Virtual Terminal Manager

## Window/Client Commands

command	key binding	description
create	CTRL-G c	Create a new client in the #1 window position and switch focus to it.
create(,,\$CWD)	CTRL-G C	Create a new client and keep the current working directory the same as the previous window.
focusnext	CTRL-G j	Switch focus to the next window.
focusprev	CTRL-G k	Switch focus to the previous window.
zoom	CTRL-G Enter	Move the currently focused window to the #1 position.
focusn(1)	CTRL-G 1	Switch focus to the specified window number, 1 through 9, without changing window positions.
focuslast	CTRL-G Tab	Switch focus to the previously focused window. Does not change any window positions.
togglerunall	CTRL-G a	Toggle to type into all visible windows at once, or just one.
toggleminimize	CTRL-G .	Toggle to minimize or unminimize the currently focused window.
focusnextnm	CTRL-G J	Switch focus to the next window, not including minimized windows.
focusprevnm	CTRL-G K	Switch focus to the previous window, not including minimized windows.
scrollback(-1)	Shift-PgUp CTRL-G PgUp	Scroll back one half page in the current window.
scrollback(1)	Shift-PgDn CTRL-G PgDn	Scroll forward one half page in the current window.
killclient	CTRL-G x x	Close the client in the currently focused window.

## Layout Commands

command	key binding	description
setLayout(NULL)	CTRL-G Spacebar	Cycle through all layouts.
setLayout("[ ]=")	CTRL-G f	Set layout to tiled with a master pane on the left and a stack on the right.
setLayout("+ + +")	CTRL-G g	Set layout to a grid of all windows.
setLayout("TTT")	CTRL-G b	Set layout to tiled with a master pane on top and a stack on the bottom.
setLayout("[ ]")	CTRL-G m	Set layout to maximized view of a single window.
setmfact("+0.05")	CTRL-G l	Increase the master pane size.
setmfact("-0.05")	CTRL-G h	Decrease the master pane size.
incnmaster("+1")	CTRL-G i	Increment the number of windows displayed in the master pane.
incnmaster("-1")	CTRL-G d	Decrement the number of windows displayed in the master pane.

## Copy &amp; Paste Commands

command	key binding	description
copymode(NULL)	CTRL-G e	Switch into the copy editor.
copymode("/")	CTRL-G /	Switch into the copy editor in search mode.
paste	CTRL-G p	Paste text from the copy buffer.

## Tag Commands

command	key binding	description
view(1)	CTRL-G v 1 CTRL-G F1	View only windows with the specified tag, 1 through 5.
toggleview(1)	CTRL-G V 1	Toggle viewing windows with the specified tag, 1 through 5, to view a group of tags.
view(NULL)	CTRL-G v 0 CTRL-G 0	View all windows from all tags.
viewprevtag	CTRL-G v Tab	View windows from previously specified group of tags.
tag(1)	CTRL-G t 1	Tag the currently focused window with only the specified tag, 1 through 5.
toggletag(1)	CTRL-G T 1	Toggle the specified tag, 1 through 5, for the currently focused window.
tag(NULL)	CTRL-G t 0	Tag the currently focused window with all tags.

## Mouse Commands

command	key binding	description
togglemouse	CTRL-G M	Toggle mouse functionality on and off.
mouse_focus	BUTTON1_CLICKED	Set focus to the selected window.
mouse_fullscreen	BUTTON1_DOUBLE_CLICKED	Set focus to the selected window and set layout to maximized.
mouse_zoom	BUTTON2_CLICKED	Set focus to the selected window and move it to the #1 position.
mouse_minimize	BUTTON3_CLICKED	Minimize the selected window.

## Application and Miscellaneous Commands

command	key binding	description
detach	CTRL-\	Detach from the session when dvtm is launched from abduco. (An abduco command.)
create("man dvtm")	CTRL-G ?	Display the dvtm manpage in a new window.
send(MOD)	CTRL-G CTRL-G	Send the literal CTRL-G character to the currently focused window.
redraw	CTRL-G CTRL-L CTRL-G r	Redraw the entire dvtm screen.
togglebar	CTRL-G s	Toggle display of the status bar on and off.
togglebarpos	CTRL-G S	Toggle the position of the status bar between top and bottom.
quit	CTRL-G q q	Quit the entire dvtm application.